

Mouse PCR Protocol (version 1)

Selection Cassette: L1L2_Bact_P



Temperature °C	Time	
94	5 min	
94	15 sec	
65	30 sec	10X (decrease 1°C/cycle)
72	40 sec	
94	15 sec	
55	30 sec	30X
72	40 sec	
72	5 min	
4	finished	

CSD-lacF: GCTACCATTACCAGTTGGTCTGGTGTC
CSD-neoF: GGGATCTCATGCTGGAGTTCTTCG
CSD-loxF: GAGATGGCGCAACGCAATTAATG

CSD-Aldh1a3-R: ATCTGGA^{AA}AAGAGGTGGCATAGGGG
CSD-Aldh1a3-ttR: GCCTCTACATTGAAATGGACCTGCC
CSD-Aldh1a3-F: GACAAAGGGGTTTCTTTTCA^{CC}CAGG

Genotype	Forward Primer	Reverse Primer	Amplicon size (bp)
Floxed	CSD-loxF	CSD-Aldh1a3-R	386
PreCre	CSD-neoF	CSD-Aldh1a3-ttR	647
PostCre	CSD-lacF	CSD-Aldh1a3-R	684
Wildtype	CSD-Aldh1a3-F	CSD-Aldh1a3-ttR	537
PostFlp	CSD-Aldh1a3-F	CSD-Aldh1a3-ttR	746
PostFlp & Cre	CSD-Aldh1a3-F	CSD-Aldh1a3-R	778

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).