

KOMP PCR Design


Mouse PCR Protocol (version 1 PK)

Design ID: 48138
Project ID: CSD31227
Selection Cassette: L1L2_Bact_P

Suggested DNA Prep: DNeasy®Tissue Kit

Reagent	1X (μL)	Cycling Parameters		
water (biological grade)	10.725	Temperature °C	Time	
betain 5M (Sigma)	6.5	94	5 min	
DMSO (Sigma)	0.325	94	15 sec	10X (decrease 1°C/cycle)
10X buffer w/o MgCl ₂ (AB)	2.5	65	30 sec	
25 mM MgCl ₂ (AB)	1.75	72	40 sec	
10 mM dNTPs (Invitrogen)	0.5	94	15 sec	30X
primers (20 μM each)	0.5	55	30 sec	
Taq 5U/μL (AmpliTaq, AB)	0.2	72	40 sec	
total cocktail	23	72	5 min	
template	2	4	finished	
reaction volume	25			

Primer Strategy



Cassette Primers

CSD-lacF: GCTACCATTACCAGTTGGTCTGGTGTGCT
CSD-neoF: GGGATCTCATGCTGGAGTTCTTCG
CSD-loxF: GAGATGGCGCAACGCAATTAATG

Gene Specific Primers

CSD-R: gcacagagttgcattagaaacctgc
CSD-ttR: tgccacttgacatttaaccacagg
CSD-F: ggtgtgtgctaccatgcgtagttag

Genotype	Forward Primer	Reverse Primer	Amplicon size (bp)
Floxed	CSD-loxF	CSD-R	265
PreCre	CSD-neoF	CSD-ttR	633
PostCre	CSD-lacF	CSD-R	563
Wildtype	CSD-F	CSD-ttR	356
PostFlp	CSD-F	CSD-ttR	524
PostFlp & Cre	CSD-F	CSD-R	503

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).