

Mouse PCR Protocol (version 1)

Selection Cassette: L1L2_Bact_P



C57BL/6N-Atm1Brd Fam92atm1a(KOMP)Wtsi/

Mmucd

Reagent	1X (μL)
---------	----------

water (biological grade)	10.725
betain 5M (Sigma)	6.5
DMSO (Sigma)	0.325
10X buffer w/o MgCl ₂ (AB)	2.5
25 mM MgCl ₂ (AB)	1.75
10 mM dNTPs (Invitrogen)	0.5
primers (20 μM each)	0.5
Taq 5U/μL (AmpliTaq, AB)	0.2
total cocktail	23
template	2
reaction volume	25

Cycling Parameters

Temperature °C	Time	
94	5 min	
94	15 sec	10X (decrease 1°C/cycle)
65	30 sec	
72	40 sec	
94	15 sec	30X
55	30 sec	
72	40 sec	
72	5 min	
4	finished	

CSD-lacF: GCTACCATTACCAGTTGGTCTGGTGTC
CSD-neoF: GGGATCTCATGCTGGAGTTCTTCG
CSD-loxF: GAGATGGCGCAACGCAATTAATG

CSD-Fam92a-R:	TGGTCACTCAAAGCAAACACACAGC
CSD-Fam92a-ttR:	GAAGGGCAACATTCCCAACTCTTCC
CSD-Fam92a-F:	CTGAAGGAGGATGCTTGGTGTTC

Genotype	Forward Primer	Reverse Primer	Amplicon size (bp)
Floxed	CSD-loxF	CSD-Fam92a-R	288
PreCre	CSD-neoF	CSD-Fam92a-ttR	652
PostCre	CSD-lacF	CSD-Fam92a-R	586
Wildtype	CSD-Fam92a-F	CSD-Fam92a-ttR	650
PostFlp	CSD-Fam92a-F	CSD-Fam92a-ttR	837
PostFlp & Cre	CSD-Fam92a-F	CSD-Fam92a-R	766

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).