

# KOMP PCR Design

Mouse PCR Protocol (version 2BW)

Design ID: 355328

Project ID: CSD89733

Selection Cassette: L1L2\_Bact\_P



MMRRC Stock #: 047758-UCD

C57BL/6N-Atm1Brd Fpr1tm1b(KOMP)Wtsi/  
Mmucl


## Suggested DNA Prep: DNeasy®Tissue Kit

Reagent	1X (µL)
water (biological grade)	10.725
betain 5M (Sigma)	6.5
DMSO (Sigma)	0.325
10X buffer w/o MgCl <sub>2</sub> (AB)	2.5
25 mM MgCl <sub>2</sub> (AB)	1.75
10 mM dNTPs (Invitrogen)	0.5
primers (20 µM each)	0.5
Taq 5U/µL (AmpliTaq, AB)	0.2
total cocktail	23
template	2
reaction volume	25

## Cycling Parameters

Temperature °C	Time	
94	5 min	
94	15 sec	
65	30 sec	10X (decrease 1°C/cycle)
72	40 sec	
94	15 sec	
55	30 sec	30X
72	40 sec	
72	5 min	
4	finished	

## Primer Strategy



## Cassette Primers

CSD-iacF: GCTACCATTACCAAGTTGGTCTGGTGTC  
CSD-neoF: GGGATCTCATGCTGGAGTTCTTCG  
CSD-loxF: GAGATGGCGAACGCAATTAAATG

## Gene Specific Primers

CSD-Fpr1-R: CCGAGATCAAAGAACCCGAATGCC  
CSD-Fpr1-ttR: CTTGGTTGGTGGTTAGTCCCTGG  
CSD-Fpr1-F2: CTGCAATGTTAACCCATCCTGTTGG

## Geneotype Forward Primer Reverse Primer Amplicon size (bp)

Geneotype	Forward Primer	Reverse Primer	Amplicon size (bp)
Floxed	CSD-loxF	CSD-Fpr1-R	284
PreCre	CSD-neoF	CSD-Fpr1-ttR	622
PostCre	CSD-iacF	CSD-Fpr1-R	582
Wildtype	CSD-Fpr1-F2	CSD-Fpr1-ttR	392
PostFlp	CSD-Fpr1-F2	CSD-Fpr1-ttR	498
PostFlp & Cre	CSD-Fpr1-F2	CSD-Fpr1-R	507

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any Flp recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).