

# KOMP PCR Design

Mouse PCR Protocol (version 1)

Design ID: 212782

Project ID: CSD 46892

Selection Cassette: L1L2\_Bact\_P



Mutant Mouse Resource & Research Centers supported by NIH

MMRRC Stock #: 048166-UCD

C57BL/6N-Atm1Brd Il10rbtm1a(KOMP)Wtsi/

Mmucd


## Suggested DNA Prep: DNeasy®Tissue Kit

Reagent	1X ( μL)
water (biological grade)	10.725
betain 5M (Sigma)	6.5
DMSO (Sigma)	0.325
10X buffer w/o MgCl <sub>2</sub> (AB)	2.5
25 mM MgCl <sub>2</sub> (AB)	1.75
10 mM dNTPs (Invitrogen)	0.5
primers (20 μM each)	0.5
Taq 5U/ μL (AmpliTaq, AB)	0.2
total cocktail	23
template	2
reaction volume	25

## Cycling Parameters

Temperature °C	Time	
94	5 min	
94	15 sec	10X (decrease 1°C/cycle)
65	30 sec	
72	40 sec	
94	15 sec	30X
55	30 sec	
72	40 sec	
72	5 min	
4	finished	

## Primer Strategy



## Cassette Primers

CSD-lacF:	GCTACCATTACCAGTTGGTCTGGTGTC
CSD-neoF:	GGGATCTCATGCTGGAGTTCTTCG
CSD-loxF:	GAGATGGCGCAACGCAATTAATG

## Gene Specific Primers

CSD-Il10rb-R:	GTATGTGTGCACGTCAGAGGTTGG
CSD-Il10rb-ttR:	GACGTTGGGATTTTCAGCTGTGTACC
CSD-Il10rb-F:	AGCTAATTACACCTCTCCAGGCTGC

## Genotype Forward Primer Reverse Primer Amplicon size (bp)

Floxed	CSD-loxF	CSD-Il10rb-R	293
PreCre	CSD-neoF	CSD-Il10rb-ttR	549
PostCre	CSD-lacF	CSD-Il10rb-R	591
Wildtype	CSD-Il10rb-F	CSD-Il10rb-ttR	527
PostFlp	CSD-Il10rb-F	CSD-Il10rb-ttR	717
PostFlp & Cre	CSD-Il10rb-F	CSD-Il10rb-R	754

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).