

KOMP PCR Design

Mouse PCR Protocol (version 1)

Design ID: 35928

Project ID: CSD37737

Selection Cassette: L1L2_gt0



MMRRC Stock #: 048561-UCD


C57BL/6N-Mdn1tm1a(KOMP)Wtsi/Mmucl

Suggested DNA Prep: DNeasy®Tissue Kit

Reagent	1X (μL)
water (biological grade)	10.725
betain 5M (Sigma)	6.5
DMSO (Sigma)	0.325
10X buffer w\o MgCl ₂ (AB)	2.5
25 mM MgCl ₂ (AB)	1.75
10 mM dNTPs (Invitrogen)	0.5
primers (20 μM each)	0.5
Taq 5U/ μL (AmpliTaq, AB)	0.2
total cocktail	23
template	2
reaction volume	25

Cycling Parameters	
Temperature °C	Time
94	5 min
94	15 sec
65	30 sec
72	40 sec
94	15 sec
55	30 sec
72	40 sec
72	5 min
4	finished

Primer Strategy



Cassette Primers

CSD-neoF: GGGATCTCATGCTGGAGTTCTTCG
CSD-loxF: GAGATGGCGAACGCAATTAATG

Gene Specific Primers

CSD-Mdn1-R: ACATGGTGGAAGGAGAGAACTGACC
CSD-Mdn1-ttR: GTAAAACCTGGTGTCTCAGTGGC
CSD-Mdn1-F: AGGTTACCCAAAACACGATCAGCG

Genotype	Forward Primer	Reverse Primer	Amplicon size (bp)
Floxed	CSD-loxF	CSD-Mdn1-R	267
PreCre	CSD-neoF	CSD-Mdn1-ttR	583
PostCre	CSD-neoF	CSD-Mdn1-R	614
Wildtype	CSD-Mdn1-F	CSD-Mdn1-ttR	444
PostFlp	CSD-Mdn1-F	CSD-Mdn1-ttR	631
PostFlp & Cre	CSD-Mdn1-F	CSD-Mdn1-R	662

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).