

KOMP PCR Design

Mouse PCR Protocol (version 2BW)

Design ID: 13851

Project ID: VG13851

Selection Cassette: ZEN-Ub1



MMRRC Stock #: 049661-UCD

C57BL/6N-Skiv2l^{tm1}(KOMP)Vl^{cg}/MbpMmucd


Suggested DNA Prep: DNeasy®Tissue Kit

Reagent	1X (μL)	Cycling Parameters	
water (biological grade)	10.725	Temperature °C	Time
betain 5M (Sigma)	6.5	94	5 min
DMSO (Sigma)	0.325	94	15 sec
10X buffer w/o MgCl ₂ (AB)	2.5	65	30 sec
25 mM MgCl ₂ (AB)	1.75	72	40 sec
10 mM dNTPs (Invitrogen)	0.5	94	15 sec
primers (20 μM each)	0.5	55	30 sec
Taq 5U/μL (AmpliTa _q , AB)	0.2	72	40 sec
total cocktail	23	72	5 min
template	2	4	finished
reaction volume	25		

10X (decrease 1°C/cycle)

30X

Primer Strategy



Cassette Primers

Reg-NeoF: GCAGCCTCTGTTCCACATACACTTCA
Reg-LacF: ACTTGCTTTAAAAACCTCCCACA

Gene Specific Primers

Reg-Skiv2l-R: GAACTTCTGTGCTGCCTTCCTTAGC
Reg-Skiv2l-wtR: GACGCATCATGGAGTCTGTGAATGG
Reg-Skiv2l-wtF2: CACAAGGACAAAGTGGTAACAAGAGC

Genotype	Forward Primer	Reverse Primer	Amplicon size (bp)
PreCre	Reg-NeoF	Reg-Skiv2l-R	710
PostCre	Reg-LacF	Reg-Skiv2l-R	910
Wildtype	Reg-Skiv2l-wtF2	Reg-Skiv2l-wtR	222

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Cre recombination, the PreCre primers may be used to identify the mutant mice. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).