

KOMP PCR Design

Mouse PCR Protocol (version 1JE)

Design ID: 11327

Project ID: VG11327

Selection Cassette: ZEN-Ub1



Stock #: 065552-UCD

C57BL/6N-Pl1ptm1.1(KOMP)Vl1cg/MbpMmucd


Suggested DNA Prep: DNeasy®Tissue Kit

Reagent	1X (μL)
water (biological grade)	10.725
betain 5M (Sigma)	6.5
DMSO (Sigma)	0.325
10X buffer w/o MgCl ₂ (AB)	2.5
25 mM MgCl ₂ (AB)	1.75
10 mM dNTPs (Invitrogen)	0.5
primers (20 μM each)	0.5
Taq 5U/μL (AmpliTaQ, AB)	0.2
total cocktail	23
template	2
reaction volume	25

Cycling Parameters

Temperature °C	Time	
94	5 min	
94	15 sec	10X (decrease 1°C/cycle)
65	30 sec	
72	40 sec	
94	15 sec	30X
55	30 sec	
72	40 sec	
72	5 min	
4	finished	

Primer Strategy



Cassette Primers

Reg-NeoF: GCAGCCTCTGTTCCACATACACTTCA
Reg-LacF: ACTTGCTTTAAAAACCTCCCACA

Gene Specific Primers

Reg-R: TGAGGCAGGTCAGAGGCTGAGG
Reg-wtF: GTCCACTGCCCTCCTCTTCACC

Reg-wtR: GCTGGGACCTGCACAGAGTACG

Geneotype Forward Primer Reverse Primer Amplicon size (bp)

PostCre	Reg-LacF	Reg-R	576
Wildtype	Reg-wtF	Reg-wtR	222

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Cre recombination, the PreCre primers may be used to identify the mutant mice. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).