

# KOMP PCR Design

Mouse PCR Protocol (version 1BW)

Design ID: 96285

Project ID: CSD26920

Selection Cassette: L1L2\_Bact\_P.



MMRRC Stock #: 050416-UCD

C57BL/6N-Atm1Brd Zbed4tm1(KOMP)Mbp/

MbpMmucd


## Suggested DNA Prep: DNeasy®Tissue Kit

Reagent	1X (μL)
water (biological grade)	10.725
betain 5M (Sigma)	6.5
DMSO (Sigma)	0.325
10X buffer w/o MgCl <sub>2</sub> (AB)	2.5
25 mM MgCl <sub>2</sub> (AB)	1.75
10 mM dNTPs (Invitrogen)	0.5
primers (20 μM each)	0.5
Taq 5U/μL (AmpliTaqa, AB)	0.2
total cocktail	23
template	2
reaction volume	25

## Cycling Parameters

Temperature °C	Time	
94	5 min	
94	15 sec	<b>10X (decrease 1°C/cycle)</b>
65	30 sec	
72	40 sec	
94	15 sec	
55	30 sec	<b>30X</b>
72	40 sec	
72	5 min	
4	finished	

## Primer Strategy



## Cassette Primers

CSD-lacF: GCTACCATTACCAGTTGGTCTGGTGTC  
CSD-neoF: GGGATCTCATGCTGGAGTTCTTCG

## Gene Specific Primers

CSD-R: CTTCTGAAAACGCACCTTGACACC  
CSD-F: TTCTCCTATATATTTAGGCCGATCCC  
CSD-wtR: CTTGTATAAACCAATGCGTGACG

## Genotype Forward Primer Reverse Primer Amplicon size (bp)

Genotype	Forward Primer	Reverse Primer	Amplicon size (bp)
PreCre	CSD-neoF	CSD-R	565
PostCre	CSD-lacF	CSD-R	516
Wildtype	CSD-F	CSD-R	183
PostFlp	CSD-F	CSD-R	397

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the PreCre primers may be used to identify the mutant mice. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line. The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).