## KOMP PCR Design

Mouse PCR Protocol (version 1)

Design ID: 55690 Project ID: CSD38776

Selection Cassette: L1L2\_Bact\_P




MMRRC Stock #: 046790-UCD C57BL/6N-Becn1tm1a(KOMP)Wtsi/Mmucd

## Suggested DNA Prep: DNeasy® Tissue Kit

Reagent	$1X (\mu L)$	Cycling Parameters		
water (biological grade)	10.725	Temperature °C	$_{ m Time}$	
betain 5M (Sigma)	6.5	94	5 min	
DMSO (Sigma)	0.325			
10X buffer w\o MgCl <sub>2</sub> (AB)	2.5	94	15  sec	1037 (1
25 mM MgCl <sub>2</sub> (AB)	1.75	65	$30  \mathrm{sec}$	$10X$ (decrease $1^{\circ}C/cycle$ )
10 mM dNTPs (Invitrogen)	0.5	_ 72	$40  \mathrm{sec}$	
primers (20 µM each)	0.5	94	$15  \mathrm{sec}$	
-		55	$30  \sec$	30X
Taq 5U/ μL (AmpliTaq, AB)	0.2	72	$40  \sec$	
total cocktail	23	$\phantom{aaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaa$	5 min	
template	2	· <del>-</del>	finished	
reaction volume	25	4	misned	

## **Primer Strategy**



Cassette Gene Specific Primers Primers

CSD-lacF: GCTACCATTACCAGTTGGTCTCTGGTGTC CSD-Becn1-R: CAGAGTGAGTTCCAAGACAGCCAGG CSD-neoF: GGGATCTCATGCTGGAGTTCTTCG CSD-Becn1-ttR: CTCCCAAGTGCTGGGATTAAAGACG CSD-loxF: GAGATGCCGCAACGCAATTAATG CSD-Becn1-F: TTGTACCGTGATTTAGGGCGTTTGC

Geneotype Forward Primer Reverse Primer Amplicon size (bp)

Floxed	CSD-lox $F$	CSD-Becn1-R	306
PreCre	CSD-neoF	CSD-Becn1-ttR	635
PostCre	CSD-lacF	CSD-Becn1-R	604
Wildtype	CSD-Becn1-F	CSD-Becn1-ttR	663
PostFlp	CSD-Becn1-F	CSD-Becn1-ttR	766
PostFlp & Cre	CSD-Becn1-F	CSD-Becn1-R	730

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).