KOMP PCR Design

Mouse PCR Protocol (version 1)

Design ID: 49131 Project ID: CSD38476

Selection Cassette: L1L2_Bact_P




MMRRC Stock #: 048124-UCD C57BL/6N-Hvcn1tm1a(KOMP)Wtsi/Mmucd

Suggested DNA Prep: DNeasy® Tissue Kit

Reagent	1Χ (μL)	Cycling Parameters		
water (biological grade)	10.725	$\overline{\text{Temperature }^{\circ}\text{C}}$	\mathbf{Time}	
betain 5M (Sigma)	6.5	94	5 min	
DMSO (Sigma)	0.325			
10X buffer w\o MgCl ₂ (AB)	2.5	94	15 sec	1037 (1 100 (1)
25 mM MgCl ₂ (AB)	1.75	65	$30 \mathrm{sec}$	10X (decrease 1°C/cycle)
10 mM dNTPs (Invitrogen)	0.5		$40 \mathrm{sec}$	
primers (20 µM each)	0.5	94	$15 \mathrm{sec}$	
Taq 5U/ μL (AmpliTaq, AB)	0.2	55	$30 \sec$	30X
1 / 1 / 2 / /		72	$40 \sec$	
total cocktail	23	72	5 min	
template	2	1	finished	
reaction volume	25	1	minimo	

Primer Strategy



Cassette Gene Specific Primers Primers

CSD-lacF: GCTACCATTACCAGTTGGTCTGGTGTC CSD-Hvcn1-R: CCTAAGCCTGTCTCAGCATCTAGGC CSD-neoF: GGGATCTCATGCTGGAGTTCTTCG CSD-Hvcn1-ttR: GATCAAATTCCAGACTTCCCTGGGC CSD-loxF: GAGATGGCGCAACGCAATTAATG CSD-Hvcn1-F: AAGAGAAACAGACTGGGTGGCTAGG

Geneotype Forward Primer Reverse Primer Amplicon size (bp)

Floxed	CSD-lox F	CSD-Hvcn1-R	322
PreCre	CSD-neoF	CSD-Hven1-ttR	529
PostCre	CSD-lacF	CSD-Hvcn1-R	620
Wildtype	CSD-Hvcn1-F	CSD-Hvcn1-ttR	667
PostFlp	CSD-Hvcn1-F	CSD-Hvcn1-ttR	774
PostFlp & Cre	CSD-Hvcn1-F	CSD-Hvcn1-R	860

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).