

Rabl6 (KO First)
Mouse PCR protocol (manual)
Design ID: 34152
selection cassette: L1L2_Bact_P

Suggested DNA Prep: DNeasy® Tissue Kit

Reagents	1X (uL)
Water (biology grade)	10.725
betain 5M (Sigma)	6.5
dmsO (Sigma)	0.325
10X Buffer w/o MgCl ₂ (AB)	2.5
25 mM MgCl ₂ (AB)	1.75
10 mM dNTPs (invitrogen)	0.5
Primers (20uM each)	0.5
taq 5U/uL (amplitaq, AB)	0.2
total cocktail	23
template	2
reaction volume	25


MMRRC Stock #: 049345-UCD

C57BL/6N-Rabl6^{tm1a(KOMP)Wtsi/Mmucd}

Cycling Parameters

Temp C	Time	
94	5 min	
94	15 sec	10X (decrease 1C/cycle)
65	30 sec	
72	40 sec	
94	15 sec	30X
55	30 sec	
72	40 sec	
72	5 min	
4	finished	

Primer strategy



Cassette Primers

CSD-lacF: gctaccattaccagttggtctggtgtc

CSD-neoF: gggatctcatgctggagttcttcg

CSD-loxF: gagatggcgcaacgcaattaatg

Gene Specific Primers

CSD-Rabl6-F GAGGTTCTGTGTAAGCACATGAACC

CSD-Rabl6-ttR GTCCCTATCCAGGTCTGCCTTGAG

CSD-Rabl6-R GGCAGGGATCTCTAAACAACCTGG

Genotypes	Primer pairs	amplicon size (bp)
Floxed	loxF & -R	263
PreCre	neoF & -ttR	615
PostCre	lacF & -R	561
Wildtype	Defb14-F & -ttR	404
PostFlp	Defb14-F & -ttR	631
PostFlp & Cre	Defb14-F & -R	618

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).