

KOMP PCR Design

Mouse PCR Protocol (version 1PK)

Design ID: 42989

Project ID: CSD39750

Selection Cassette: L1L2_Bact_P



MMRRC Stock #: 049765-UCD

C57BL/6N-Slco2b1tm1a(KOMP)Wtsi/Mmucd

Suggested DNA Prep: DNeasy®Tissue Kit

Reagent 1X (μL)


water (biological grade)	10.725
betain 5M (Sigma)	6.5
DMSO (Sigma)	0.325
10X buffer w/o MgCl ₂ (AB)	2.5
25 mM MgCl ₂ (AB)	1.75
10 mM dNTPs (Invitrogen)	0.5
primers (20 μM each)	0.5
Taq 5U/μL (AmpliTaQ, AB)	0.2
total cocktail	23
template	2

reaction volume 25

Cycling Parameters

Temperature °C	Time	
94	5 min	
94	15 sec	10X (decrease 1°C/cycle)
65	30 sec	
72	40 sec	
94	15 sec	30X
55	30 sec	
72	40 sec	
72	5 min	
4	finished	

Primer Strategy



Cassette Primers

CSD-lacF: GCTACCATTACCAAGTTGGTCTGGTGTG
CSD-neoF: GGGATCTCATGCTGGAGTTCTTCG
CSD-loxF: GAGATGGCGCAACGCAATTAATG

Gene Specific Primers

CSD-R: ATAGCCAAGGAGAGCCTAGAACTTC
CSD-ttR: ATAGCTGGGAAGTCAAGGTCAGCCT
CSD-F: agatgggtctcagcgtaatgctactc

Genotype Forward Primer Reverse Primer Amplicon size (bp)

Floxed	CSD-loxF	CSD-R	283
PreCre	CSD-neoF	CSD-ttR	647
PostCre	CSD-lacF	CSD-R	581
Wildtype	CSD-F	CSD-ttR	463
PostFlp	CSD-F	CSD-ttR	633
PostFlp & Cre	CSD-F	CSD-R	616

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).