KOMP PCR Design

Mouse PCR Protocol (version 1)

Design ID: 88532
Project ID: CSD30582
Selection Cassette: L1L2_Bact_P

MMRRC @ UCDavis
Mutant Mouse Resource & Research Centers supported by NIH

MMRRC Stock #: 049768-UCD
C57BL/6N-Slit1tm1a(KOMP)Wtsi/HMmucd

Suggested DNA Prep: DNeasy®Tissue Kit

Reagent	1X (µL)
water (biological grade)	10.725
betain 5M (Sigma)	6.5
DMSO (Sigma)	0.325
10X buffer w\o $MgCl_2$ (AB)	2.5
25 mM $MgCl_2$ (AB)	1.75
10 mM dNTPs (Invitrogen)	0.5
primers (20 µM each)	0.5
Taq 5U/ µL (AmpliTaq, AB)	0.2
total cocktail	23
template	2
reaction volume	25

Cycling Parameters		
Temperature °C	**Time**	
94	5 min	
94	15 sec	
65	30 sec	**10X (decrease 1°C/cycle)**
72	40 sec	
94	15 sec	
55	30 sec	**30X**
72	40 sec	
72	5 min	
4	finished	

Primer Strategy



Cassette Primers	
CSD-lacF:	GCTACCATTACCAGTTGGTCTGGTGTC
CSD-neoF:	GGGATCTCATGCTGGAGTTCTTCG
CSD-loxF:	GAGATGGCGCAACGCAATTAATG

Gene Specific Primers	
CSD-Slit1-R:	TGTTTGATCCCAGCATGCAGTTTCC
CSD-Slit1-ttR:	AACCCTCCTGTACCACCATTGAAGG
CSD-Slit1-F:	AGTCTCTGTTCCCTCTCCCTCTACC

Genotype	Forward Primer	Reverse Primer	Amplicon size (bp)
Floxed	CSD-loxF	CSD-Slit1-R	388
PreCre	CSD-neoF	CSD-Slit1-ttR	544
PostCre	CSD-lacF	CSD-Slit1-R	686
Wildtype	CSD-Slit1-F	CSD-Slit1-ttR	591
PostFlp	CSD-Slit1-F	CSD-Slit1-ttR	743
PostFlp & Cre	CSD-Slit1-F	CSD-Slit1-R	880

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).