

KOMP PCR Design

Mouse PCR Protocol (version v1JE)

Design ID: 35791

Project ID: CSD37217

Selection Cassette: L1L2_gt2



MMRRC Stock #: 050217-UCD

C57BL/6N-Trim45tm1a(KOMP)Wtsi/Mmucd


Suggested DNA Prep: DNeasy®Tissue Kit

Reagent	1X (μL)
water (biological grade)	10.725
betain 5M (Sigma)	6.5
DMSO (Sigma)	0.325
10X buffer w/o MgCl ₂ (AB)	2.5
25 mM MgCl ₂ (AB)	1.75
10 mM dNTPs (Invitrogen)	0.5
primers (20 μM each)	0.5
Taq 5U/μL (AmpliTaq, AB)	0.2
total cocktail	23
template	2
reaction volume	25

Cycling Parameters

Temperature °C	Time	
94	5 min	
94	15 sec	10X (decrease 1°C/cycle)
65	30 sec	
72	40 sec	
94	15 sec	30X
55	30 sec	
72	40 sec	
72	5 min	
4	finished	

Primer Strategy



Cassette Primers

CSD-neoF: GGGATCTCATGCTGGAGTTCTTCG
CSD-loxF: GAGATGGCGCAACGCAATTAATG

Gene Specific Primers

CSD-R: AAGCCTGATCCTGAAGGTTCTTGG
CSD-ttR: CATGGGATACATCTTCAAAGGTGC
CSD-F: TGTGAGCAGTCCCTGCCTTTCC

Genotype	Forward Primer	Reverse Primer	Amplicon size (bp)
Floxed	CSD-loxF	CSD-Cbx7-R	260
PreCre	CSD-neoF	CSD-Cbx7-ttR	634
PostCre	CSD-neoF	CSD-Cbx7-R	607
Wildtype	CSD-F	CSD-Cbx7-ttR	397
PostFlp	CSD-F	CSD-Cbx7-ttR	513
PostFlp & Cre	CSD-F	CSD-Cbx7-R	485

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by your facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).