KOMP PCR Design

Mouse PCR Protocol (version 1)

Design ID: 197895 Project ID: CSD66797

Selection Cassette: $L1L2_Bact_P$



MMRRC Stock #: 050404-UCD


C57BL/6N-Atm1Brd Yap1tm1a(KOMP)Mbp/

MbpMmucd

Suggested DNA Prep: DNeasy® Tissue Kit

Reagent	1X (μL)	Cycling Parameters	i e	
water (biological grade)	10.725	Temperature $^{\circ}$ C	${f Time}$	
betain 5M (Sigma)	6.5	94	$5 \min$	
DMSO (Sigma)	0.325	94	15 sec	
$10X$ buffer w\o MgCl ₂ (AB)	2.5			1037 (1 100 / 1)
25 mM MgCl ₂ (AB)	1.75	65		10X (decrease 1°C/cycle)
10 mM dNTPs (Invitrogen)	0.5	72	$40 \mathrm{sec}$	
` ,		94	$15 \mathrm{sec}$	
primers (20 µM each)	0.5	55	$30 \sec$	30X
Taq 5U/ μL (AmpliTaq, AB)	0.2	72	$40 \sec$	5011
total cocktail	23			
template	2	72	5 min	
reaction volume	$2\overline{5}$	4	finished	

Primer Strategy



Cassette Gene Specific Primers Primers

CSD-lacF: GCTACCATTACCAGTTGGTCTGTGTC CSD-Yap1-R: TCAAGGCCATCATAGATCCTGGACG CSD-neoF: GGGATCTCATGCTGGAGTTCTTCG CSD-Yap1-ttR: TAAAACCCAAGCTACAGGGGACAGG CSD-loxF: GAGATGGCGCAACGCAATTAATG CSD-Yap1-F: CTCACAGAGATCCTCCTGTCTCAGC

Geneotype	Forward Primer	Reverse Primer	Amplicon size (bp)
Floxed	CSD-loxF	CSD-Yap1-R	341
PreCre	CSD-neoF	CSD-Yap1-ttR	626
PostCre	CSD-lacF	CSD-Yap1-R	639
Wildtype	CSD-Yap1-F	CSD-Yap1-ttR	509
PostFlp	CSD-Yap1-F	CSD-Yap1-ttR	631
PostFlp & Cre	CSD-Yap1-F	CSD-Yap1-R	639

Please note, these primers are auto-designed and may not have been verified by the repository, and as such may require optimization or redesign by vour facility.

We recommend running primers singleplex. For screening of pups prior to any Flp or Cre recombination, the Floxed or PreCre primers may be used to identify the mutant mice. The Floxed primers test for the distal LoxP site. The PostCre primers should be used if mutant mice were crossed with a Cre recombinase line (without any FLP recombination). The PostFlp primers should be used if mutant mice were crossed with a Flp recombinase line. The PostFlp & Cre primers should be used if mutant mice were crossed with a Flp recombinase line and then a Cre recombinase line. The wildtype primers should be used for zygosity testing of all mutant mice (pre or post recombination).